

Recording

1. Recording is only enabled for the 1XY display mode, and only for the 'Block Erase with Dot' or 'Continuous Erase with Dot' erase modes.
2. Remember to create a data directory in the Setup window prior to recording data.

Footswitch Recording:

3. Using the menu bar select **Recording** -> **Footswitch Record**, or if Buttons are enabled click on **Footswitch**.
4. Click on **RUN** and data will begin streaming.
5. Begin recording by pressing the footswitch.
6. The **Recording Light** will illuminate to indicate recording is active.
7. Even though the screen is erasing per the selected erase mode, all data is being saved.
8. To stop recording and save the file, press the footswitch a second time. The **Recording** light will turn off, and the program will display the file name being saved.
9. The **Tubelist Index** will increment by one, and then the flying dot will display live data.
10. At this point the program is waiting for another footswitch event to begin recording the next data file.
11. At any point, to stop recording click on the **STOP** button.

Auto Record:

1. Auto Record uses a routine to constantly monitor the acquired data and automatically saves data to file when the probe is determined to be out of the tube.
2. Auto Record should not be used if both channels are connected to differential probes.
3. The **Timer** object located just above the **Record** selector is used to delay the out-of-tube flag so that the probe can exit the back of a tube, and be pulled back without triggering a 'save file' action.
4. The **Timer** has a default setting of 1.5 seconds and is user adjustable from 1 to 4 seconds.
5. The **Timer** object setting is only accessible when the **Charts** window is in the 'Button' mode.

6. Using the menu bar select **Recording** -> **Auto Record**, or if Buttons are enabled click on **Auto** in the **Record** object.
7. The status display will instruct the operator to move the probe into free space (away from any metal) and click on **Balance**.
8. To begin recording click on **RUN**, then insert the probe into a tube.
9. The program will recognize that the probe is in a tube and the **Recording** indicator will illuminate.
10. Data will erase from the screen per the selected erase mode, but all data will continue to be stored until the probe is withdrawn from a tube for a time period exceeding the **Timer** setting.
11. With the probe out of the tube the **Recording** object will turn off, and the program status display will indicate the file name saved.
12. The **Tubelist Index** will increment by one, and then the flying dot will display live data.
13. At this point the program is waiting for the probe to enter the next tube.
14. At any point to stop recording click on the **STOP** button.
15. As needed, use the **Previous**, **Next**, and **Tubelist Index** objects to adjust the Tubelist to repeat or overwrite recorded data.